

How to Check the of Setup Microsoft Outlook Express

With Microsoft Outlook Express open click "Tools", "Accounts..."

Internet Accounts			<u>? x</u>
All Mail News	Directory Service		<u>A</u> dd ►
Account	Туре	Connection	<u>R</u> emove
	mail (default)	Any Available	<u>P</u> roperties
			Set as <u>D</u> efault
			Import
			<u>E</u> xport
			<u>S</u> et Order
			Close

Click on the "Mail" tab, and then the "Properties" button

Click on the "Servers" tab, and then near the bottom of this window check the "My server requires authentication" box

膏 mail.s	easurf.net F	Properties	? ×
General	Servers C	onnection Security Advanced	
Server	Information –		_
<u>M</u> y ir	ncoming mail	server is a POP3 server.	
Inco	ming mail (PO	P3): mail.ipinc.net	
0 <u>u</u> tg	oing mail (SM	TP): atlas.ipinc.net	
Incomir	ng Mail Serve	ı ————	_
A <u>c</u> co	ount name:	j.doe	
<u>P</u> ass	word:	•••••	
		☑ Remember password	
Πι	.og on using 🖞	Secure Password Authentication	
Outgoir	ng Mail Serve	r	-
	∕ly ser <u>v</u> er reqi	ires authentication S <u>e</u> ttings.	
		OK Cancel <u>A</u> p	ply

Click on the "Advanced" tab, change the "Outgoing mail [SMTP]:" to 587, change the "Server Timeouts" to 3 minutes, and then click the "OK" button

General Servers Connection Security	y Advanced	
Server Port Numbers		
Outgoing mail (SMTP): 587	<u>U</u> se [Defaults
🔲 This server reguires a secule conr	nection (SSL)	
Inconing mail (POP3): 110		
This server requires a secule <u>c</u> onr	nection (SSL)	
Server Timeouts Short Long 3 Sending	minutes	
Break apart messages larger than	60	K3
Delivery)
Leave a copy of messages on ser	ver	
Γ Bemove from server after 5	day(s)	
Remove from server when dele	ted from 'Deleted	ltems'
OK	Cancel	Apply

Next click the "Close" button and you are done

©2000-2007 Seasurf Internet a division of Internet Partners, Inc. 1800 NW 167th Place Suite 160 Beaverton, Oregon 97006-8132 Phone Seaside +1 503 738 3844 Phone Beaverton +1 503 690 2700 FAX +1 503 690 9700